



Advidia VP-8 and VP-16 Upgrade Instructions


1. Login to the camera with admin/12345 as the password
2. Go to Configuration\Remotely Upgrade:




3. Browse to the location you saved the digicap file to:




4. Click OK to begin the firmware upgrade:




5. The upgrade will take several minutes to complete. **DO NOT POWER CYCLE OR REMOVE THE DEVICE FROM THE NETWORK:**



6. Once the Upgrade is complete, select Now to reboot the device:



7. Select Ok and close the Remote Setting page:



The device will take around 2 minutes to reboot. Once it has finished click on Remote Config and select Version Information to ensure the upgrade was successful:

